

SuperVAG Installing Guide

Notice:


- Please install this SuperVAG software in WIN-7 Pro system.
If install in Windows 10, you need to change the compatibility mode to Windows 7
- Your computer HDD must have at least 3 disk drive(C: D: E:), or, instead, you can use a USB Flash Drive or additional HDD to plug into your computer.

Steps:

1. copy the software into your computer from the CD, unzip it.
2. First install **JAVA**.
* you can use the newer Java, but please change COM to be COM3 and, WIN 7 must be WIN 7 Professional version.

JAVA32位.exe	50,265,184	50,063,205	应用程序	2016/2/26 星...	48911160
JAVA64位.exe	63,109,184	60,811,549	应用程序	2016/11/20 ...	2CB9A0...

3. Click **SETUP**, run it as administrator.



4. If you didn't install the Java first, the software can't be installed successfully.

How to change COM port:

Device Manager - Ports (COM& LPT) - SuperVAG COM - Right click and click on 'Properties'- Click on 'Port Settings' - click on 'Advanced' - 'COM Port Number'- Click on that to change it to be your required COM Port.